
## How to Create Panoramic Images with Just a Tripod

Dennis Freeman – 4/25/2019

## Why do Panoramas?


- A panoramic photograph has a wide format. The ratio between height and length of the photo is 1:2<sup>+</sup>. The field of view is greater than 100°, and frequently exceeds the angle of human vision (~140°).
- Why not do an iPhone Pano?
  - Less control of perspective (straight lines curve)
  - Only 72 dpi. Need more for large prints and good projectors.
  - JPEG: Raw format has more image information: much wider dynamic range and larger color space. Editing can push the images a lot further, bringing out and rescuing hidden detail in the darkest shadows and brightest highlights.
- Why not use a wide angle lens? (and crop)
  - Wide angle lens may not be wide enough
  - Undesirable lens distortion
  - With larger prints get more pixels from pano than in single shot.
  - Can use general purpose zoom lens

# Wide Angle May Not Be Wide Enough:



## Camera Equipment

- **Digital Camera** Need the exposure (aperture, shutter speed and ISO) to be locked. Ideally, want to shoot in full Manual mode (preferably a DSLR).
- **Lens** Zoom lenses are the most useful. Fixed/prime lenses work, but being able to zoom in and out will give you more versatility. Any midrange zoom lens such as a 24-70mm is great.
- Lens Filters Recommend taking filters off your lens. It is OK to keep a clear (e.g. UV) filter on, as long as it is not introducing any vignetting to your images on the wide end. Remove a circular polarizer if you have one mounted on your lens, because it will mess up your sky. E.g.:



## Camera Equipment, con't

- **Tripod** Highly recommended for best results. The head needs to be able to pan from left to right with ease.
- Arrange camera in Portrait orientation (requires camera L-bracket when using tripod).



• Cable Release – optional, but recommended for capturing shake-free images. 2 sec shutter delay is good too.

## Settings

- Shoot in "Manual" mode
- **ISO** turn off "Auto ISO". Set to fixed value, e.g. camera base ISO (either 100 or 200) for sunny day.
- Aperture and Shutter Speed want everything in focus. Set aperture to preferably f/10+ (depending on nearest foreground object). Then set shutter speed based on the meter reading as explained below.
- Metering try to find a "sweet middle" and set your shutter speed based on entire panorama. Take a couple of pictures and make sure that the images are not too overexposed or underexposed for the brightest and darkest parts of the scene.
- **Shoot in raw** (optional) Lightroom Classic CC provides a raw pano.
- White Balance set to "Sunny", "Cloudy", etc not "Auto WB".
- Lens Focal Length wide-angle lenses below 24-28mm (full-frame) and 16-18mm (APSC) can have heavy distortion and vignetting issues that can make it difficult to properly align and stitch images.
- Set your lens to Manual Focus
- When using tripod, turn lens Image Stabilization off.

### Steps


#### Take a Test Shot in "Aperture Priority" Mode

- First, to identify the correct exposure settings, switch to Aperture Priority mode, set the aperture to f/11, focus, then take a test shot of the brightest part of the scene.
- Check that the test shot has enough sharpness in the foreground and the background. If it doesn't, then increase your aperture value, e.g. to f/16, adjust focus, and take another test shot.
- Double-check that there are no blown highlights in your test image. If you
  do find blown highlights adjust shutter speed or ISO until you get a good
  test shot.

#### Select "Manual Mode"

- Apply Aperture, Shutter Speed, and ISO settings
- Set White Balance to fixed value of "Sunny", "Cloudy", etc.
- Make sure that the focus is on manual and set properly.
  - Image Stabilization is off if using tripod.
- Cable Release plugged in to camera or shutter release delayed (e.g. 2 sec)
- Level the ball head and tripod:

## You Need to Level The Tripod & Ball Head



Unlevel tripod and ball head causes stitching problems

### Level & Vertical Axis of Rotation



Need the tripod head to be level and need the ball head mounting stem to be vertical.

This ensures that the ball head panning action occurs around the vertical axis.

How do we do this?

### Put Ball Head on Level Table

Center clamp's bubble (or use a level) to get stem vertical.



- You can get your ball mounting stem perfectly vertical in your house before you go outside. Take the ball head off the tripod and set it on a level counter top.
- Adjust the ball so that the bubble is perfectly centered, then lock it down. (If your clamp doesn't have a built-in bubble, you can balance a small level across the top of the mounting clamp).
- Lock down the ball.
- Reattach ball head to tripod.

Set Just the Ball Head on a Level Table

## Level Tripod & Ball Head Pair

Center clamp's bubble (or use a level) to get Ball head & tripod level


by adjusting the leg lengths where the tripod is going to be while taking the pano shots.



Now attach camera, loosen panning lock on ball head, and check camera and lens settings

## Steps, con't

- Start from the left side of the pano
- Take a shot and remember a spot in the image that is going to be the left edge of the 2nd image, providing for ~30% 50% overlap.



 Rotate camera to right and take 2<sup>nd</sup> shot, remembering a spot in the image that is going to be the left edge of the 3rd image ...

# Example: Great Falls, Olmsted Island, MD

- Canon 5D Mark IV full-frame camera
- Canon 24-105mm f/4L lens at 43mm focal length
- Tripod & Ballhead no special pano gear
- Portrait orientation with camera L-bracket
- Manual Mode, f/20, 1/160 sec., ISO 400, WB: "Sunny"
- 8 shots, overlapped by ~30%

## 8 Overlapped Photos (Great Falls, MD)















## Apply Panorama Software

#### Photo Stitching Software to Create Panoramas

- Hugin
- Microsoft Image Composite Editor
- PTGui Pro
- AutoPano Pro
- Panorama Stitcher
- iFoto Stitcher
- Adobe Lightroom Classic CC
- Adobe Photoshop CC
- Lightroom Classic


#### Me: Lightroom Classic CC:


- In image folder select all images to be used in pano (all will turn light gray when selected)
- Select Photo > Photo Merge > Panorama
- Select a projection.
- After preview is displayed, click on "Merge"

## Open Image Folder



# Select All (click on #1, Shift-click on #7): They turn light gray.







Click on

> Photo > Photo Merge > Panorama

**Select "Cylindrical" or "Perspective"** 

Wait for preview ...





Click on Merge if it looks good

## Lightroom: Select a Projection

- **Spherical**: Aligns and transforms the images as if they were mapped to the inside of a sphere. This projection mode is great for really wide or multirow panoramas.
- **Perspective**: Projects the panorama as if it were mapped to a flat surface. Since this mode **keeps straight lines straight**, it is great for architectural photography. Really wide panoramas may not work well due to excessive distortion near the edges of the resulting panorama.
- **Cylindrical**: Projects the panorama as if it were mapped to the inside of a cylinder. This projection mode works really well for wide panoramas, but it also keeps vertical lines straight. (Selected in example)





Post-processing: crop, clarity, vibrance



Lesson: Allow for extra vertical coverage!

# Example #2: Great Falls, Olmsted Island, MD

- Canon 5D Mark IV full-frame camera
- Canon 16-35mm f/2.8L lens at 16mm focal length
- Tripod & Ballhead no special pano gear
- Regular Landscape orientation
- Manual Mode, f/20, 1/160 sec., ISO 400, WB: "Sunny"
- 4 shots, overlapped by ~30%

## 16mm Wide Angle Pano

16-35mm Canon f/2.8 L at 16mm. Tripod. Manual Focus, "Sunny" WB. Manual Mode: f/20, 1/160 sec, ISO 400











Lightroom Panorama




**ERROR** 



16mm lens distortion prevents stitching.
But Lightroom can fix that!

## 16mm Wide Angle Pano, con't



## 16mm Landscape Pano - Final



Post-Processing: Cropped, Clarity, Vibrance

# Example #4: Great Falls, Olmsted Island, MD

- Canon 5D Mark IV full-frame camera
- Canon 24-105mm f/4L lens at 43mm focal length
- Handheld but same thing happens with tripod
- Portrait orientation
- Manual Mode, f/20, 1/160 sec., ISO 400, WB: "Sunny"
- My buddy "Smiley" joined for his portrait.
- 7 shots, overlapped by ~30%
  - Group of people on left avoided

## Handheld – Object in foreground


Foreground Smiley OK, but wooden bannister warped.



Lightroom – Pano with "Cylindrical" Projection


## Handheld – Object in foreground

Straightens wooden bannister, but Smiley is upset.



Lightroom – Pano with "Perspective" Projection

## Why is Smiley messed up?




- Camera parallax during rotation has moved foreground objects against their backgrounds between individual images.
- Smiley is shifted closer to rock in 2<sup>nd</sup> image.
- Stitching software having trouble identifying tie points between images.
- Shifting and warping isn't right.
- Some subjects aren't the best when doing handheld panoramas. Try avoiding foreground objects. The following example does this:

### Panorama at Lake Artemesia




You needn't go far for a handheld panorama subject. Here is a ten image panorama from Lake Artemesia in College Park - actually Berwyn Heights. (Lake Artemesia Map) Note that there aren't any foreground objects that span multiple images. Just a bush in the right image, and a bit of a bush in the left image. They aren't involved in the overlap stitching, and this scene would be fine with just a tripod and ball head.

### How to Fix Parallax



 If you really want to be able to do panoramas without cherry picking your venue to avoid foreground objects then you have to bite the bullet and remove parallax.



 Gearing up can solve this. The details are covered in another presentation.







